

“SUMO Donations”

Created : 23/03/2016

Updated : 04/09/2017

Description:

Sumo Donations is a Complete WooCommerce Donation System. Using this plugin you can provide options for the User to donate to your site. Donations can be made in the Single Product Page, Cart Page, Checkout Page, Donation Form and Fly Box.

Features:

- **Complete Donation System**
- **Percentage of Cart Subtotal as Automatic Donation**
- **Donation in Product Page**
- **Donation in Cart Page**
- **Donation in Checkout Page**
- **Separate Form for Donation**
- **Fly Box for Donation**
- **Rewards for Making Donations**
- **Highly Customizable**
- **Compatible with SUMO Subscriptions**
- **Translate Ready**
- **WPML Compatible**
- **and more**

Getting Started With SUMO Donations:

How to Install:

1. Login to your **codecanyon** account
2. Go to Downloads Tab
3. You will find **SUMO Donations**

4. Download **sumodonations.zip** (Please note the downloaded files will always be the latest version)
5. Unzip **sumodonations.zip** inside which you will find the Plugins files i.e. **donationsystem.zip**
6. Install **SUMO Donations** i.e. **donationsystem.zip** using WordPress Dashboard
7. Activate the Plugin

How to Upgrade to a newer version of SUMO Donations?

Please always test the new version on a testing site before you upgrade to the new version in your live site.

If you are using an older version and want to upgrade to the latest version of SUMO Donations, then please do the following steps.

1. Login to your **codecanyon** account
2. Go to **Downloads** Tab
3. You will find **SUMO Donations**
4. Download **sumodonations.zip** (Please note the downloaded files will always be the latest version)
5. Unzip **sumodonations.zip** inside which you will find the Plugins files i.e. **donationsystem.zip**
6. **Deactivate** and **Delete** the existing version of **SUMO Donations** on your site
7. Install the latest version of **SUMO Donations** i.e. **donationsystem.zip** using WordPress Dashboard
8. Activate the Plugin

Please note you will not lose any settings values, data etc by following the above steps.

Support

Please check the documentation as we have lots of information there. For support, feature request or any help, please [register and open a support ticket on our site](#).

Work Flow of SUMO Donations

SUMO Donations Supports the following options

- Percentage of Cart Subtotal as Automatic Donation
- Donation Form Using Separate Form
- Donation Form In Single Product Page
- Donation Form In Cart Page
- Donation Form in Checkout Page
- Donation using Fly Box.

Percentage of Cart Subtotal as Automatic Donation

- Percentage of Cart Subtotal can be set by the Site Admin
- User adds a \$100 product to the Cart.
- The Percentage of Cart total is set as 20 Percent.
- A donation product with Cost of \$20 will be automatically added to cart and cannot be removed.
- User proceeds to the checkout page and completes the order.

Donation Using a Separate Form

- Separate Donation Form can be Created using a Short code.
- User can Select any one Donation amount from the predefined Donation amounts.
- A Donation Product will be added to the Cart.
- The User can Proceed to Checkout page and pay for the donation product like a normal Product Purchase.

Donation Form in Single Product Page

- User is Currently viewing the Product Page.
- A Donation Form is displayed with a predefined amount and an option to donate.
- User Clicks the Donate Button.
- A Donation Product will be added to the Cart.
- The User can Proceed to Checkout page and pay for the donation product like a normal Product Purchase.

Donation Form in Cart Page

- User is Currently at the Cart Page.
- A Donation Form is displayed with an option for the User to enter an amount and donate.
- User enters an amount and Clicks the Donate Button.
- A Donation Product will be added to the Cart..
- The User can Proceed to Checkout page and pay for the donation product like a normal Product Purchase.

Donation Form in Checkout Page

- User is Currently at the Checkout Page.
- A Donation Form is displayed with an option for the User to enter an amount and donate.
- User enters an amount and Clicks the Donate Button.
- A Donation Product will be added to the Cart.
- The User can pay for the donation product.

Donation Using a Fly Box

- User is currently in Cart Page or Checkout Page.
- A Fly box Appears when the user scrolls to the bottom of the page with an option to Donate for the Site.
- The User Chooses to donate and clicks on any one of the Predefined Amounts.
- A Donation Product will be added to the Cart..
- The User can Proceed to Checkout page and pay for the donation product like a normal Product Purchase.

Setting Up SUMO Donations

In order for SUMO Donations to Work, a Donation Product has to be Created. The Donation Product can be an Existing Product in the Site or a New Product can be created as a Donation Product.

- To Create a Donation Product Go to **WooCommerce - > Sumo Donation -> General**
- If you choose to use an Existing Product as a Donation Product, In the **Product that should be used for Donation Product** option select an Existing product and click save.
- If you choose to create a New Product as a Donation Product, In the Donation Product Setup option, select **Create New Product**.
- Click on the **Create New Donation Product Button**.

- In the **Product that should be used for Donation Product** option select the newly created product and click save.

Adding Automatic Donations to Cart

Go to **WooCommerce -> Sumo Donations -> Automatic Donation**

- Enable the Automatic Donation based on Cart Total option
- Choose the type of Product for Automatic Donation Product.
- Select an Existing Product or create a new Product.
- Set the Percentage of Cart Total that should be used as Donation Amount.
- By default, the Donation amount can be calculated from all Products. If you to restrict it to certain Products, that can be done by using the **Product** option.

Displaying the Donation Form Using a Form

Go to **WooCommerce -> Sumo Donations -> General**

- Create a new Page.
- Paste the short code **[fp_donation_table]** in the Page.
- Publish the Page.

Displaying the Donation Form in Product Page

Go to **WooCommerce -> Sumo Donations -> Donation Form**

- Enable the **Show Donation Form in Product Page** option.
- The Type of the Donation Field has to be selected.
- The Minimum and Maximum Values for Contribution can be set.
- Click on Save Changes.

Note:

1.) By default, the Donation Form in Product Page will be displayed for All Products. If you want to Restrict it to certain Products, it can be done using the **Show Donation Form in** option.

2.) For Non Editable Text field, the default Value has to be entered.

Displaying the Donation Form in Cart Page

Go to **WooCommerce -> Sumo Donations -> Donation Form**

- Enable the **Show Donation Form in Cart Page** option.
- The Type of the Donation Field has to be selected.

- The Minimum and Maximum Values for Contribution can be set.
- Click on Save Changes.

Displaying the Donation Form in Checkout Page

Go to **WooCommerce - > Sumo Donations -> Donation Form**

- Enable the **Show Donation Form in Checkout Page** option.
- The Type of the Donation Field has to be selected.
- The Minimum and Maximum Values for Contribution can be set.
- Click on Save Changes.

Displaying the Donation Form Using Fly Box

Go to **WooCommerce - > Sumo Donations -> Fly Box**

- Enable the **Show Fly Box** option.
- The Type of the Donation Field has to be selected.
- The Minimum and Maximum Values for Contribution can be set.
- Click on Save Changes.

Note: The Donate button can be customized using the Custom Class.

Force Manual Donation

Go to **WooCommerce - > Sumo Donations -> General -> Donation Settings for Manual**

- Select **Force Manual Donation** Check box.
- Save the settings.

Note: In this scenario if user try to place the order without donating, the order will not be completed and error message will be displayed.

Forcing Automatic Donation to Cart

Go to **WooCommerce - > Sumo Donations -> Automatic Donation**

- Select Force Automatic Donation check box.
- Choose the type of Donation Value for Automatic Donation Product in Automatic Donation Value option.
- If % of Cart Total is selected in Automatic Donation Value option, Enter the percentage value in Percentage of Cart Total as Donation field.
- If you wish to include the tax, then select Include tax check box.
- If you wish to reduce the Donation Value from cart total, then select

Donation Value subtracted from cart total in Donation Value Added/Subtracted option. If you want to add, then select Donation Value Added to Existing Cart Total option.

- If Fixed Value is selected in Automatic Donation Value option, then you have set the Fixed Value in Fixed Value as Donation field.
- Save the settings.

Rewarding the User for Making a Donation

- You can Reward your Users by gifting them a free product for making a donation.
- The Free products which are to be gifted can be controlled based on the Minimum and Maximum Donation range.

To set the Free product

Go to **WooCommerce - > Sumo Donations -> Donation Rewards**

- Click on the Add Rule Button.
- The Minimum and Maximum Donation range has to be entered.
- The Free product can be selected from the list of products available in the site.
- If the User Donates within the specified Range, the user will be eligible for a Free product. This free product can be added to the User's Cart or can be listed for the User to choose based on the option selected in **Add Donation Rewards Type** option.
- Multiple Rules can be created by clicking the Add Rule Button.
- If Multiple Rules are created, then the priority of the rule will be calculated based on the option selected in **Rule Priority** option.

Displaying the List of Contributors

- Create a new Page.
- Paste the short code **[fp_donation_table]** in the Page.
- Publish the Page.

Plugin Compatibility

SUMO Subscriptions

When used with SUMO Subscriptions, recurring donations can be made by users. A Subscription product created using SUMO Subscriptions can be set as a Donation.

How to Setup SUMO Donations such that it supports Recurring Donation?

- Create a Simple Subscription product(without Trial and Signup fee)
- If you want to set the Subscription Donation to be Manual, then go to **WooCommerce - > SUMO Donations - > General - > Donation Product Settings**.
- Select **Existing Product** in **Donation Product Setup** drop-down menu.
- Choose the Subscription product which was created by searching the product name in **Product that should be used for Donation(Product should be non-taxable and non-shippable)** search box.
- If you want to set the Subscription Donation to be Automatic, then go to **WooCommerce - > SUMO Donations - > Automatic Donation - > Automatic Donation Settings**.
- Check the **Enable Automatic Donation** checkbox.
- Select **Existing Product** in **Donation Product Setup** drop-down menu.
- Choose the Subscription product which was created by searching the product name in **Product that should be used for Donation(Product should be non-taxable and non-shippable)** search box.

FAQ

1. Which are the places to display donation form?

- Any page or post using short code
- Cart Page
- Checkout Page
- Fly box in Cart Page
- Single product page

2. Can the fly box be displayed in any page or post?

The fly box is displayed only on the cart page provided donation has not been made

3. What product must be set as donation product?

Any new or existing product that is non taxable and non shippable can be set as donation product.

4. What is the use of the donation product?

A Donation product is used to make donations in the WooCommerce shop. The donation made is set as the price of the donation product and hence making donation is similar to purchasing a product in the WooCommerce shop.

5. Should i set the donation product?

Yes, only after you set the donation product, users can make donations in your site.

6. Will it work for both Guests and Members?

Yes, it will work for both Guests and Members.

Requirements

The minimum server requirements and the WordPress requirements are as follows

- PHP 5.2.4 or greater, MySQL 5.0 or greater
- WordPress 3.4 or Higher
- WooCommerce 2.0 +

Browser Compatibility

SUMO Donations works fine with all major browsers such as IE8.0 +, Mozilla, Chrome, Safari, Opera etc.

Documentation Updated:

This Documentation has been updated for Recover Abandoned Cart Version 1.8.

Theme Compatibility

SUMO Donations should work fine with all the top themes.